

Collar Cleaning User Guide

Updated 2024-04-19

Sections

1. Processing GPS Data (Collar Cleaning)
2. Filter and Rarify Data

Collar Cleaning

1. PROCESSING GPS DATA

Processing of GPS data is brand specific.

The user location where the download happens and the time of year (DST or not) can affect local time processing for some models.

It is recommended that the user keep a log of When/Where the collar data is downloaded.

PROCESSING GPS DATA

AKA COLLAR CLEANING

Folder Organization

- Programs assume a hierarchy
 - C/D/E
 - Wolf-Projects
 - Data
 - » locdataAll-CCv31
 - Original (cleaned collar data all in the same folder)
- cc program will generate
 - “<filename>_analysis” as input to cluster program
 - “<filename>_location” as input to merge programs
- If original files are organized within sub-folders then csvCopy.py program can be used
 - Note: change the path names to flatten all of the collar files to a single folder

cc_v35.py

- cc == CollarClean
- Note: if the files are edited with Excel versus notepad++ it is important to set the column formats of any date columns to YYYY-MM-DD
- To run program: (Python 2.7.15)
 - Copy program into folder containing raw csv files
 - Open with IDLE
 - Run Module
- Review and keep log file generated
- Change Date Range if necessary
 - # Global variables for date range selection
 - # default to no selection - program always checks for date range file
 - daterange_parsed= False - if external date range file parsed
 - daterange_flag = False - if external date range defined
 - daterange_start = "2016-01-01" - default, can be overridden by external file
 - daterange_end = "2018-12-31" - default, can be overridden by external file

cc_v35.py

- # Date adjustment flags – important issue
 - televiltDSTpresent = 1 # set to 1 if the file was **downloaded** during DST
 - televiltDSTremove = 1 # set to 1 to remove DST
- ```
– if (televiltDSTpresent == 1):
– print ' >>> '
– print ' >>> DST Present'
– print ' >>> '
– if (televiltDSTremove == 1):
– print ' >>> '
– print ' >>> DST Removed'
– print ' >>> '
– else:
– print ' >>> '
– print ' >>> DST NOT Removed'
– print ' >>> '
– else:
– print ' >>> '
– print ' >>> DST NOT Present'
– print ' >>> '
```

# Time Terminology


- UTC – is the Universal Coordinated Time
- GMT – is a time zone in England
- UTC == GMT w.r.t. actual time
- DST
  - In regions where daylight saving time is used, it commences on the second Sunday of March, and standard time restarts on the first Sunday in November.
- Local Time – may be affected by DST
- LMT: not commonly used
  - Keep headers the same and assume LMT == LocalTime (LT)



# Date/Time Fields – cc\_v35

| Collar Type | Date/Time Local | Local DST                                            | Date/Time GMT | Date/Time in Location<br>YYYY-MM-DD | Date/Time in Analysis<br>(Input to Cluster Analysis)<br>MM/DD/YYYY | Note                                                                           |
|-------------|-----------------|------------------------------------------------------|---------------|-------------------------------------|--------------------------------------------------------------------|--------------------------------------------------------------------------------|
| ATS         | Y               | N                                                    | N             | Local                               | Local                                                              |                                                                                |
| Lotek       | Y               | N                                                    | Y             | Local                               | Local                                                              |                                                                                |
| Sirtrack    | N               | N                                                    | Y             | Calc Local from GMT                 | Calc Local from GMT                                                |                                                                                |
| Televilt    | Y               | Y<br>(based on date and location of actual download) | N             | Calc Local (no DST)                 | Calc Local (no DST)                                                | LOCATION MATTERS!<br><br>This code assumes download in same timezone as collar |
| Telonics    | N               | N                                                    | Y             | Calc Local from GMT                 | Calc Local from GMT                                                |                                                                                |

Set flags in cc program



# cc program limitations (cc\_v35)

- Folder names can not contain “\_”
- Folder names cannot contain a collar type e.g. Televilt
- Multiple Sirtrack Formats
  - Need to resave CSV UTC date column in YYYY-MM-DD format
- Multiple Televilt Formats
- Lotek: ignore original dateTimeGMT field
  - Instead use gmtDate, gmtTime
- Hard coded Lat and Long checks may need to be tweaked based on study area
  - Check lat outside range [50,60] → error
  - Check long outside range [-108,-97] → warning

The cleaned collar data `_location` and `_analysis` files may not match 1:1 given the slightly different rules in the `cc` program.

This step will result in the `_location` files being further cleaned then filtered and rarified into 4 sub-folders

## **2. FILTER, CLEAN & RARIFY DATA**

# Manual Edits

- Manual Editing of the cleaned files may be necessary given the data collection methods adopted for the research project.
- Case 1: Initial period after Collaring
  - Remove all rows up to the following day GMT time (> 24 hours from local time of collaring)
- Case 2: Mortality/Collar drop-off
  - Remove all rows on that same day – local time

# Program: rarifyWloc\_v5.R

- Create: aaaControlFile.csv
- Run program
- Review and save R log into a file
- Check folders (R1/R2all/R2even/R2odd)

# aaaControlFile

- WolfID: select wolf id
- FilterS: remove any reading  $\leq$  FilterS (seconds) default == 60s (deferred)
- gen2Hall: generate 2 hour rarified data using all points (flag (0 or 1))
- gen2Heven: generate 2 hour rarified data using even points (flag (0 or 1))
- gen2Hodd: generate 2 hour rarified data using odd points (flag (0 or 1))
- Implied:
  - 1HourLowS == 1800
  - 1HourHiS == 2HourLowS = 5400
- Dropped: Epsilon to detect Even/Odd
  - Only 12 points were affected by rounding with Epsilon == 15 minutes

# aaaControlFile – sample input

|    | A      | B       | C        | D         | E        |
|----|--------|---------|----------|-----------|----------|
| 1  | WolfID | filterS | genR2all | genR2even | genR2odd |
| 2  | W01    | 0       | 1        | 0         | 1        |
| 3  | W02    | 0       | 1        | 0         | 1        |
| 4  | W03    | 0       | 1        | 1         | 0        |
| 5  | W04    | 0       | 1        | 1         | 1        |
| 6  | W05    | 0       | 1        | 1         | 0        |
| 7  | W06    | 0       | 1        | 1         | 0        |
| 8  | W07    | 0       | 1        | 1         | 0        |
| 9  | W09    | 0       | 1        | 0         | 1        |
| 10 | W10    | 0       | 1        | 1         | 0        |
| 11 | W11    | 0       | 1        | 1         | 1        |
| 12 | W12    | 0       | 1        | 0         | 1        |
| 13 | W13    | 0       | 1        | 1         | 1        |
| 14 | W14    | 0       | 1        | 1         | 1        |
| 15 | W15    | 0       | 1        | 1         | 1        |
| 16 | W16    | 0       | 1        | 1         | 1        |
| 17 | W19    | 0       | 1        | 1         | 1        |
| 18 | W20    | 0       | 1        | 1         | 1        |
| 19 | W21    | 0       | 1        | 1         | 1        |
| 20 | W22    | 0       | 1        | 1         | 1        |
| 21 | W24    | 0       | 1        | 1         | 1        |
| 22 | W25    | 0       | 1        | 1         | 1        |
| 23 | W26    | 0       | 1        | 1         | 1        |
| 24 | W27    | 0       | 1        | 1         | 1        |
| 25 |        |         |          |           |          |

# Folders

- Folders Used:
  - R1: rarified to 1 hour
  - R2all: rarified to 2 hours
  - R2even: only even points, rarified to 2 hours
  - R2odd: only odd points, rarified to 2 hours



# FILTER RULES

- Orig == original lines read from file
- Cleaned == Orig – (Lat/Long out of range)
- Filtered == not implemented
- SelectedEO == num of points (even or odd)
- Rarified ==
  - num of points with step size > rareLimits
- Flag == “.” iff location file == analysis file

# aaaRarityLog.csv – sample output

|    | A      | B      | C          | D                                          | E    | F       | G        | H          | I        | J    |
|----|--------|--------|------------|--------------------------------------------|------|---------|----------|------------|----------|------|
| 1  | Folder | WolfID | rareLimits | File                                       | Orig | Cleaned | Filtered | SelectedEO | Rarified | Flag |
| 2  | R1     | W27    | 1800       | ATS_W27_AD_2017021420171204_location.csv   | 6595 | 6595    | 6595     | 6595       | 6585     | .    |
| 3  | R1     | W27    | 1800       | ATS_W27_AD_2017021420171204_analysis.csv   | 6595 | 6595    | 6595     | 6595       | 6585     | .    |
| 4  | R2all  | W27    | 5400       | ATS_W27_AD_2017021420171204_location.csv   | 6595 | 6595    | 6595     | 6595       | 3397     | .    |
| 5  | R2all  | W27    | 5400       | ATS_W27_AD_2017021420171204_analysis.csv   | 6595 | 6595    | 6595     | 6595       | 3397     | .    |
| 6  | R2even | W27    | 5400       | ATS_W27_AD_2017021420171204_location.csv   | 6595 | 6595    | 6595     | 3315       | 3305     | .    |
| 7  | R2even | W27    | 5400       | ATS_W27_AD_2017021420171204_analysis.csv   | 6595 | 6595    | 6595     | 3315       | 3305     | .    |
| 8  | R2odd  | W27    | 5400       | ATS_W27_AD_2017021420171204_location.csv   | 6595 | 6595    | 6595     | 3280       | 3271     | .    |
| 9  | R2odd  | W27    | 5400       | ATS_W27_AD_2017021420171204_analysis.csv   | 6595 | 6595    | 6595     | 3280       | 3271     | .    |
| 10 | R1     | W01    | 1800       | Lotek_W01_GL_2016011820160309_location.csv | 685  | 682     | 682      | 682        | 641      | .    |
| 11 | R1     | W01    | 1800       | Lotek_W01_GL_2016011820160309_analysis.csv | 682  | 682     | 682      | 682        | 641      | .    |
| 12 | R2all  | W01    | 5400       | Lotek_W01_GL_2016011820160309_location.csv | 685  | 682     | 682      | 682        | 637      | .    |
| 13 | R2all  | W01    | 5400       | Lotek_W01_GL_2016011820160309_analysis.csv | 682  | 682     | 682      | 682        | 637      | .    |
| 14 | R2odd  | W01    | 5400       | Lotek_W01_GL_2016011820160309_location.csv | 685  | 682     | 682      | 679        | 637      | .    |
| 15 | R2odd  | W01    | 5400       | Lotek_W01_GL_2016011820160309_analysis.csv | 682  | 682     | 682      | 679        | 637      | .    |
| 16 | R1     | W02    | 1800       | Lotek_W02_WW_2016012020160527_location.csv | 1835 | 1604    | 1604     | 1604       | 1540     | .    |
| 17 | ---    | ---    | ---        | -----                                      | ---- | ----    | ----     | ----       | ----     | ---- |

# rarifyWloc: File Processing I

- Read control file
- For each input file (\_location)
  - Determine Wolf ID
  - Apply existing checks
    - # Remove rows where Lat == 0 or Long == 0
    - alldata = alldata[alldata\$Latitude!=0,]
    - alldata = alldata[alldata\$Longitude!=0,]
    - # remove NA rows
    - alldata = alldata[!is.na(alldata\$Latitude),]
    - alldata = alldata[!is.na(alldata\$Longitude),]
    - # remove out of range rows
    - alldata = alldata[alldata\$Longitude <= -97.0,]
    - alldata = alldata[alldata\$Longitude >= -108.0,]
  - Check \_location and \_analysis files are the same length
  - If filterS <> 0
    - Apply FilterS
  - Create an OrigFixNum – so that the points can be traced back to the original points
  - This is important because Cluster Analysis needs FixNum's in strict numeric order

Deferred – not needed

# rarifyWloc: File Processing II

- For each input file (`_location`, `_analysis`)
  - Rarify 1 hour
    - Use `1HLowS` as limit
    - Write `R1` files
  - If `gen2Hall`
    - Rarify to 2H using `2HourLowS` as lower bound
    - Write `R2all` files
  - If `gen2Heven`
    - Select even hours
    - Rarify to 2H using `2HourLowS` as lower bound
    - Write `R2even` files
  - If `gen2Hodd_f`
    - Select odd hours
    - Rarify to 2H using `2HourLowS` as lower bound
    - Write `R2odd` files

# checkWloc\_v1: Check the Rarified Files

- Program checks: Id, Lat, Long
- Run program
- Review and save R log in a file
- As an extra check we want to ensure that the corresponding location and analysis files match exactly